1. 在PC机上安装控制程序(L4-7 Application, 以V3.60为例)

(1) 源程序目录(以H盘为例进行说明):

H:)		
最 新建文件夹		
名称	修改日期	英型
3.47	2014/9/13 21:31	文件夹
100781960.Spirent TestCenter Layer 4-7 Application_3.60	2011/3/3 16:55	应用程序
📶 wireshark-win32-1.4.2-Spirent	2010/12/6 11:03	应用程序

(2) 安装 "TestCenter L4~7 Application" 软件

名称	▼ 修改日期	英型	大小
100781960.Spirent TestCenter Layer 4-7 Application_3.60	2011/3/3 16:55	应用程序	476,204 KB

(3) 安装完毕时,提示安装"TestCenter Application"软件。



2. 在PC机上TestCenter程序(以V3.47为例)

(1) 源程序目录(以H盘为例进行说明):

名称	-	修改日期	类型	大小
Spirent TestCenter Application 3.47		2010/6/5 7:49	应用程序	212,502 KB

(2) 按提示步骤安装,安装过程状态如下:

Spirent TestCenter Application - InstallShiel	d Vizard 🛛 🔀
Setup Status	A.
The InstallShield Wizard is removing Spirent TestCenter Application	
Uninstalling	
C:\\Content\access_multicast\ppp\pppox_view_results.htm	
InstallShield	
	Cancel

(3) "TestCenter应用程序"安装结束时,弹出如下对话框,选择[是]:

Question	
?	Spirent Device Commander and Tcl interpreter installation are required to run External Device Commands from both STC GUI and command sequencer.
	Click 'Yes' button to install Spirent Device Commander. Tcl Interpreter can be downloaded from Spirent support site (http://support.spirentcom.com)
	是(Y) 吞(N)

(4) 进一步出现提示信息,选择[是]:



- 3. 安装TCL文件
 - (1) 在第一步所说文件夹中,选择"TCL"安装文件,并按提示安装:

Select Spir	ent Device (Commander Installer	? 🛛
查找范围(I):	C Testcenter	3.70_Setup_140708	
我最近的文档	101729042.S TCL 8.4.13 wireshark w	pirent TestCenter Application for Spirent TestCenter Automation in32-1.4.2-Spirent	
桌面			
一次 我的文档			
我的电脑			
西北部王	文件名(图):	13 for Spirent TestCenter Automation 💌	打开@
	文件类型(I):	Executable files (*. exe)	取消

(2) "TCL"安装结束

TCL - InstallShield	Vizard
	TCL - InstallShield Wizard The InstallShield Wizard has successfully installed TCL. Click Finish to exit the wizard.
	KBack Finish Cancel

- 4. 安装"WireShark应用程序",按提示进行即可。
- 5. 启动 "TestCenter应用程序",设置"TCL"和"Wireshark"路径:
 - (1) 启动应用程序: Spirent TestCenter Layer 4-7 Application 3.60 快速方式
 - (2) "TCL"路径:



Kelp					
 Appearance Confirmation Dialoge Confirmation Dialoge Submat Profiles Submat Profiles Partis Sayres Tratis Partis Results Tab Gaseral Nighlights Datails Throbaits Basager Subscellancess May Editor Strictloneter Signed Harden User Fase Spirent Test Expert 	Spirent TestCente Fath to Dil Interpret Fath to Initialia	x xx xx xx xx xx xx xx xx xx	in SOUTHD + TIMF (C) Program Files Spirent Cennu Opirent Test TCL DIS 共享文档	Ireess	× * * * * * * * * * * * * *

(3) "WireShark" 路径(该步骤可选):

mander		
stration Help	(Li col
iii ≜ ?	0 NH	(e.com
) Preferences	·····································	_
Help Appearance Confirmation Dialogs Confirmation Confirmation	a diameter a diameter a dids a editcap a dids a editcap a beip a rawshark b bip a text2pcap a plugins a text2pcap a text a text2pcap a text a text2pcap a text a text2pcap a text a text b text a text	1开 取消

注: "c:\Program Files"为Windows XP系统下的默认安装路径,在Windows 7系统下,默认安装路径为"c: \Program Files(x86)"。

6. 导入license。

